

Aqua Conserve, Inc.


Version 8.94

Addendum

Overview:

The Aqua Conserve software update contains the following changes.

1. The LOCK feature has been removed.
2. The Accumulation feature is an option. From the factory ET-6, 9, 14 8B, and 12B controllers will have accumulation disabled. ET-16, 24, 32 and Ultimo controllers will have the feature enabled and turned off.



Enable Accumulation:

Turn **Dial** to the *Settings* position.

Simultaneously press the **Previous** and **Next** keys.
The display will change to show the Number of Stations screen.


Simultaneously press the **Previous** and **Next** keys again.
The display will change to show the Accum OPT screen.

Press the **More** key to enable the Accumulation option.

Press the **Less** key to disable the accumulation option.

Press the **Next** key to return to the Settings screen.

Refer to your manual for information on the Accumulation Option.



IMPORTANT

When the Accumulation Option is enabled the Accumulation option is set to OFF. You must go to the Settings Screen and turn the Accumulation on.

